

Manual:Extension/BlueSpicePermissionManager

A quality version of this page, approved on *11 December 2019*, was based off this revision.


Contents

1 Access to the permission manager	2
2 Role-based permissions	2
2.1 Default roles	. 3
3 The roles matrix	4
3.1 Role inheritance	5
4 Technical info	5
4.1 Logging	5
4.2 Backups	5
5 Related info	. 5



Access to the permission manager

To manage permissions, the extension **BlueSpicePermissionManager** provides the administrator interface. It is located under *Global actions > Management > Permisison manager*. This links to the page Special:PermissionManager :



Role-based permissions

In BlueSpice version 3.0 roles were introduced as a way to manage wiki rights, . The main intention of using roles is to simplify rights management.

Roles represent a **collection of individual permissions** that are necessary to perform certain function on the wiki. For example, for a user who is supposed to only read the wiki, many permissions in addition to the "read" permission are needed: the ability to change their own settings, to search the wiki, to view page ratings, and so on.

All permissions that make up a logical group are encapsulated in a role, in this example the role "reader". If wiki admins want to grant read-only rights to a user group, they only need to assign that group the "reader" role, instead of assigning many individual rights.

By assigning roles to a group, all users belonging to that group will receive the rights contained in these roles. Roles are not assigned directly to users, but to groups instead. Users are then assigned to one or more groups.



Default roles

By default, BlueSpicePermissionManager includes a number of pre-defined roles that serve most user needs on the wiki. The individual permissions contained in a role can be seen by clicking the info icon in front of the role name. It opens a dialog with a permissions list for the role:

🚰 bot		
···· 🎦 bureaucrat	🕑 bot	
🔡 editor	 maintenancead 	dmin
🎦 reviewer 🛛 🔽 Ca	ancel	Done
Smwadminis		
- Smwcurator	I	Permissions in role: bot
sysop		Export table 🗸
···· 📽 visitor		
widgeteditor Pe	ermission \uparrow	Description
ar	pihighlimits	Use higher limits in API queries
au	utoconfirmed	Not be affected by IP-based rate limits
au	utopatrol	Have one's own edits automatically marked as patrolled
au	utoreview	Have one's own edits automatically marked as "checked"
au	utoreviewrestore	Auto-review on rollback
bl	luespiceabout-viewspecia	Access to the special page [[Special:BlueSpiceAbout]]
bo	ot	Be treated as an automated process
cł	Modify the values of checklist items without editing the wiki	

- **bot** typically assigned only to the *bot* group
- **admin** all available rights. It should be assigned only to wiki-admin groups
- **maintenanceadmin** very similar to the *admin* role, used for user groups that are responsible for maintaining wiki integrity
- **author** all permissions necessary for creating content on the wiki
- editor create content, edit and delete content, create reviews
- **reviewer** all reviewing actions
- accountmanager user account management rights
- structuremanager move (rename) pages, create and delete namespaces
- reader basic read-only access
- accountselfcreate this role must be assinged to the "*" groups to allow users to self-create user accounts
- commenter cannot create and edit content, can only comment on existing content



The roles matrix

The permission manager consists of the group tree (1) and the role matrix (2):

Special									User
								User talk	
Permission manager								BlueSpice	
									BlueSpice talk
Save Reset Show system groups								Export table 🗸	File
				N	amespaces				File talk
- 🗁 user	Role	Wiki	(s	QM	_		S		MediaWiki
- ** autoreview	2	~	(Pages)		Portal	Síaff	Minutes	3	MediaWiki talk
1 – 💒 bot									Template
- 🐭 bureaucrat	bot						Columns >	Namespaces 🗦	Template talk
- 🐭 editor	maintenanceadmin								Help
- 💒 restrictedsysop	admin								🗌 Help talk 🖉
- 🎥 reviewer	admin								Category
- 🎥 smoketest	author								Category talk
- 🕍 smwadministrator	editor								Property
- 🕍 smwcurator	reviewer								Property talk
- 🐭 sysop	accountmanager								Form
widgeteditor	accountinanager								Form talk
	structuremanager								Concept
	reader								Concept Talk
	accountselfcreate								Widget
	commenter								Widget talk
	commenter								Module
									Module talk
									Blog
									Book

The **group tree** (on the left) shows all existing groups:

- Group "*": all non-logged-in (anonymous) users
- Group "user": all logged-in users, the default group for all users
- **Subgroups of group "user":** all groups that are defined on the wiki, eiter by default, by MediaWiki, or custom groups created by the wiki admins. System groups, created by MediaWiki, can be hidden by unchecking the "Show system groups" checkbox above the tree.

The columns in the **role matrix** are:

- **Role information** (info icon): Clicking the icon shows all the permissions in a role. This list is exportable.
- Role name
- **Wiki:** Assignment of a role to the entire wiki. By assigning the role in this column, a user group gets permissions in this role on the wiki (all namespaces).

Manual:Extension/BlueSpicePermissionManager

- BlueSpice
 - 1 ediaWiki
 - Individual namespaces: The following columns list every (applicable) namespace on the wiki.
 - ^O Roles can be assigned to individual namespaces. For example, the group *user* can get the *editor* role only in the namespace *Public. Users in this group cannot edit content in any other*. By granting a role to a particular group in a particular namespace, means that all other groups will lose permissions from this role, eg. granting role "reader" in namespace "Private" to group "sysop" means that all users in any other groups won't be able to read pages in "Private" namespace, even if they have "reader" role granted on the wiki level ("Wiki" column).
 - $^{\circ}$ The same role can be granted to multiple groups for the same namespace.
 - Additional namespaces can be added in the matrix by clicking on the arrow in table header, then "Columns". Then the namespaces can be selected.

Role inheritance

By default, all roles granted to the (*) group will be granted to the *user* group, and all roles granted to the *user* group are granted to its subgroups. If a group inherits the role from an upper-level group field, this is indicated in the role matrix with a green background, but the checkbox is empty.

Technical info

Logging

Every change to the roles is logged in the MediaWiki log book, found under Special:Log under Permission Manager log type. These logs are available only to wiki administrators (users in groups with the role *admin*).

Backups

All changes to the role matrix are backed up. By default, the last 5 backups are kept. This limit can be changed in BlueSpiceConfigManager, under configs for the extension BlueSpicePermissionManager.

• **Backup limit:** Sets the number of backups for the permissions manager. Each time the page *Special: PermissionManager* is saved, a backup is created. If the backup limit is set to 5, the last five versions of the permissions configuration are saved as backups.

Related info

- Reference:PermissionManager
- Managing groups
- Rights concepts