

Manual: Extension/BlueSpiceUniversalExport/Customization

Compatibility info: In BlueSpice pro Cloud, it is possible to adjust some PDF template settings directly in the wiki. In other editions, the adjustments need to be made directly on the server. These instructions only explain the functionality in the Cloud.

Header and footer

By default, the PDF template contains 3 sections for the header and 3 sections for the footer.





Product Info Header

What is BlueSpice?

With BlueSpice MediaWiki you enable your employees to quickly access current and business-critical knowledge via a central and dynamic knowledge base. BlueSpice is an open-source enterprise software that offers you many advantages: It is stable, secure, and relies on state-of-the-art web technologies. You retain control over the source code and ensure that all developments remain publicly available. In keeping with the open-source philosophy, there is also a free distribution in addition to the paid editions pro and farm.

System requirements

BlueSpice is delivered with the latest LTS (long-term support) version of MediaWiki. BlueSpice is tested by Hallo Welt! for use on Windows and Linux systems. To make sure you can use the latest version with no hassle, we recommend that you consider our system requirements.BlueSpice pro on our servers (Cloud)

Many small and medium-sized companies start with a cloud solution. We will install and maintain the software or set up and support the server for you. We provide a preconfigured and passwordprotected system that is accessible from any web-enabled device. You enjoy the advantages of the cloud: regular, automatic updates, optimal server performance through adapted resource distribution and elastic scaling. A connection of your authentication server via SAML is optionally possible.

BlueSpice pro on your own server (On Premises)

Most of our customers run their BlueSpice on their own servers (Windows or Linux) in-house, thus ensuring optimum integration into their IT infrastructure. If the server has very high loads, then you can scale up the operation to several servers. Connections to user directories and central backup systems, operation behind firewalls and proxies, and integration with intranet portals are possible.

External content from Office products can be migrated to BlueSpice pro. Alterations to the software and the integration of additional MediaWiki extensions on your own server are no problem. We would be happy to help you with the installation and setup of BlueSpice pro.

Footer

23.12.2020

Dieses Dokument wurde erzeugt mit BlueSpice

5

6

1/1

Standard PDF template



Both the content and the number of columns in the header and footer area can be edited in the following files.

- MediaWiki:UniversalExport/PDF/Default/Header.html
- MediaWiki:UniversalExport/PDF/Default/Footer.html

Available parameters

The following content can be added to each section in the header or footer:

Parameter	Description
logo	current wiki logo
title	title of the page. In books, this is the title of the book page.
subtitle	
currentpagenumber	number of the current page
totalpagescount	total number of pages
url	URL of the wiki page
user	username of user who printed the page
exportdate	date of PDF-creation
exporttime	time of PDF-creation

Each parameter is added to the header or footer enclosed in three curly brackets, for example: $\{\{\{\log o\}\}\}\}$.

In addition, you can simply type in regular text in each section.

Customizing the header

The header contains a wiki table with three columns. The default content for the first column is the logo of the wiki and the last column shows the page title. The middle column is empty.

To make changes to the header:

1. Open the page *MediaWiki:UniversalExport/PDF/Default/Header.html* in edit mode.





