

Univention

BlueSpice is available as App for the Univention Corporate Server. It is delivered via the Univention App Center and can be easily installed.

Furthermore BlueSpice is available as appliance: it can be used in a virtual environment with the Univention Corporate Server as basis operating system.

Contents	
1 Administration of the App	
1.2 Add more users	2
2 Install Appliance	3
3 Trouble shooting	
4 Web links	4



Administration of the App

Assign user

To login at your BlueSpice MediaWiki users must be assigned in the UCS system and domain settings.

- 1. Open System and Domain Settings
- 2. Select **Users**, open -> **Users Management of domain users** and select user.
- 3. Open Apps and select the check mark at "Activate user for BlueSpice MediaWiki".

Add more users

Adding more users does not work via the BlueSpuce User Manager but via the UCS user management.

- 1. Open System and Domain Settings.
- 2. Select **Users**, open -> **Users Management of domain users** and **Add** new user.
- 3. Do not forget to open Apps and select the check mark at "Activate user for BlueSpice MediaWiki".



Install Appliance

The steps to install the BlueSpice appliance









Start of the appliance

Select languages

Domain and network configuration

Domain setup









Set account information and Administrator password (important!)

Host settings

Confirm configuration settings

Setup success confirmation









Get IP to open the Univention Corporate Server in your browser

Upload license key, which you get via email

Login as Administrator and with your administrator password Your applications: open first the system and domain configuration





Assign user
(Administrator) in
the central
authentication
system for
BlueSpice. Now you
can start the wiki
and login as
Administrator

Trouble shooting

It a known issue, that UCS under specific conditions changes the IP and user can not authenticate at the BlueSpice MediaWiki. Univention is working on that.

To fix that problem

- 1. Open System and Domain Settings.
- 2. Select **Domain**, open -> **LDAP Browsing and managing the LDAP tree**.
- 3. Select in the tree in the left navigation bar under your Domain name: computers dc ucs-<ID>
- 4. Check and change IP adress (3 times) and Save.

Web links

- Univention App Center
- Univention Wiki